For Research Use Only

SpeedAb WB Kit for Mouse IgG2a

Catalog Number: SW003



www.ptgcn.com

产品介绍

SpeedAb Western Blot Kits are ideal for fast western blot workflows, cutting down protocol time of your experiment to ~2h, while also minimizing hands-on time.

The Kit combines two Proteintech products:

FlexAble HRP enables single step detection by fast & easy labeling of your primary antibody with an HRPconjugated FlexLinker. FlexAble labeling can be done in under 20 min, requires no additional material, works with any Rabbit IgG (Proteintech #SW001), Mouse IgG1 (#SW002), Mouse IgG2a (#SW003), or Mouse IgG2b (#SW004) antibody from any supplier, in almost every buffer system, at any concentration.

Learn more about FlexAble: https://www.ptglab.com/products/flexable-antibody-labeling-kits/ Blotting Accelerator reduces incubation times per antibody to ~15min without sacrificing result quality. Learn more about Blotting Accelerator: https://www.ptglab.com/products/-TM-WB--PR20039.htm When combined, these two components facilitate easy, and reliable 1 step detection using rabbit antibodies

Product Codes for specific Kits:

(FlexLinkers are species specific and will only work with the correct IgG subtype)

(SW001) Rabbit IgG (SW002) Mouse IgG1 (SW003) Mouse IgG2a (SW004) Mouse IgG2b

in 15 minutes.

产品成分

Component CatalogNo. Size FlexAble HRP Antibody Labeling Kit for Mouse IgG2a KFA045 10 rxns **Blotting Accelerator** PR20039 100 mL

FlexAble HRP Kits: Store for 1 year at -20°C or for 6 months at 4°C upon receipt. Avoid exposure to light. **Blotting Accelerator:** Store at 2-8℃ for a year.

Sizing is based on a standardized antibody incubation volume of 5 mL Blotting Accelerator (single step detection) and a recommended dilution of 1:5000, with 0.5 ug of antibody used per Blot.

Example:

20 rxns

Recommended dilution of primary antibody: 1:5000

Volume of Accelerator per reaction: 5000 uL

Volume of antibody needed: 1 uL Antibody concentration: 0.5 ug/uL Amount of antibody to conjugate: 0.5 ug Amount of FlexAble reactions needed: 1 rxn

Scale volumes & amounts according to recommended dilution of your primary antibody.

We recommend using a minimum of 1 uL FlexLinker, even if the antibody to be labeled is less than 0.5 ug (e.g. in cases when recommended dilution for WB is very high).


If you need help calculating your exact volumes, use our FlexAble Calculator

Tool: https://www.ptglab.com/FlexCalc

包装规格 保存条件

使用方法

Validation Data



SpeedAb WB Kit for detection of mouse IgG2a. (red) Classical Western blot detection of PCNA in lysates from different human cell lines. A primary anti-HSP90 antibody (mouse IgG2a) was used in combination with a secondary anti-mouse antibody (HRP), after blocking and incubation with antibodies for 1 h, respectively. The total time of ~... hincludes SDS-PAGE, blotting, blocking, primary and secondary antibody incubation, and washing steps of the membrane. (blue) Detection of HSP90 in lysates from different human cell lines via SpeedAb WB Kit. The same primary anti-HSP90 antibody was labeled with FlexAble HRP (antimouse IgG2a) via a simple 10 min protocol, enabling a 1-step detection. The blotting accelerator speeds up binding of the antibody to the target protein, cutting the antibody incubation time to 15 min only and the total time including SDS-PAGE, blotting, antibody incubation and a final washing step to ~2 h.